



Updating drumatom and drumatom Player

1 Installation

You can find the new installers for drumatom and drumatom Player in your accuSONUS account under “Downloads” tab (<http://www.accuSONUS.com/dashboard#downloads>).

As with any standard software update, installing the new drumatom and drumatom Player versions **will overwrite** previous versions. DAW projects using drumatom Player will load normally.

To activate your products, please see the “Activation manual” which can be found here: <http://www.accuSONUS.com/sites/default/files/u69/manuals/Activation%20manual.pdf>.

You can *uninstall* the previous drumatom and drumatom Player versions if you want, before installing the new versions, to avoid any possible problems or conflicts.

2 Uninstalling drumatom

2.1 Mac

drumatom is a standalone application. To remove it from your Mac system you can go to your “Applications” folder, right click on drumatom and move it to your “Trash” (Figure 1).

2.2 Windows

To remove drumatom from your Windows system, you can use the “Control Panel → Programs and features” (Windows 7, 8) or “Settings → Apps and features” (Windows 10). Find “Drumatom v2.1” and choose uninstall (Figure 2).




Figure 1: Uninstalling drumatom in Mac OS




Figure 2: Uninstalling drumatom in Windows

3 Uninstalling drumatom Player

3.1 Mac

To remove drumatom Player from Mac OS, follow these steps: Open “Finder” and select “Go →Go to folder...” from the menu. You can also use the keyboard shortcut (⌘+ ⌥+ G). This will bring up the screen shown in Fig. 3. You need to go to the following folders and remove these four files:

1. /Library/Audio/Plug-ins/Components/Drumatom.component
2. /Library/Audio/Plug-ins/VST/Drumatom.vst
3. /Library/Application Support/Avid/Audio/Plug-ins/Drumatom.aaxplugin
4. /Library/Application Support/Digidesign/Plug-ins/Drumatom.dpm




Figure 3: Entering a path in finder

3.2 Windows

To remove drumatom Player from your Windows system, you can use the “Control Panel →Programs and features” (Windows 7, 8) or “Settings →Apps and features” (Windows 10). Find “drumatom Player v1.1” and choose uninstall (see Fig. 4).




Figure 4: Uninstalling drumatom Player in Windows